Particle interactions with matter

All particle detecting techniques are based on interactions of particles with different materials

Short-range interaction with nuclei

- Probability of a particle to interact (with a nucleus or another particle) is called cross-section.
 - **(a)** Cross-sections are normally measured in *millibarns*: $1 mb \equiv 10^{-31} m^2$
 - Output Description of a reaction is sum over all possible processes

There are two main kinds of scattering processes:

- In the second secon
- inelastic scattering: final state particles differ from those in initial state, like in $π^-p → K^0 Λ$



Figure 47: Cross sections of π^- on a fixed proton target

- For complex nuclei, cross-sections are bigger, and elastic scattering on a nucleon can cause nuclear excitation or break-up – *quasi-elastic scattering*

Knowing cross-sections and number of nuclei per unit volume in a given material *n*, one can introduce two important characteristics:

In the second s

In the second s

At high energies, short-range nuclear interactions involve mainly hadrons, facilitating their detection.

Neutrinos and photons have much smaller cross-sections of interactions with nuclei, since former interact only weakly and latter – only electromagnetically.

Ionization energy losses

• Energy loss per travelled distance : dE/dx

Important for all charged particles

Mostly due to Coulomb scattering of particles off atomic electrons



Figure 48: Energy loss rate for pions in copper. At low β , dE/dx is proportional to $1/\beta^2$. At high β , dE/dx proportional to ln(β)

Bethe-Bloch formula for spin-0 bosons with charge $\pm e$ (e.g. π^+, π^-, K^+, K^-):

$$-\frac{dE}{dx} = \frac{Dn_e}{\beta^2} \left[ln \left(\left(\frac{2mc^2 \beta^2 \gamma^2}{I} \right) - \beta^2 - \frac{\delta(\gamma)}{2} \right) \right]$$
(35)

$$D = \frac{4\pi\alpha^2\hbar^2}{m} = 5.1 \times 10^{-25} MeV cm^2$$

In Equation (34), $\beta = v/c$ is velocity (p = mv); n_e , *I* and $\delta(\gamma)$ are constants which are characteristic to the medium:

- (a) n_e is the electron density, $n_e = \rho N_A Z / A$, where ρ is the mass density of the medium and A is its atomic weight. Hence, energy loss is strongly *proportional to the density* of the medium
- \bigcirc *I* is the mean ionization potential, *I* \approx *10Z eV* for *Z*>*20*
- $\odot \delta(\gamma)$ is a dielectric screening correction, important only for very energetic particles.

Radiation energy losses

Electric field of a nucleus accelerates or decelerates particles, causing them to radiate photons, hence, lose energy: *bremsstrahlung* (literally, "braking radiation")

Bremsstrahlung is an important source of energy loss for light particles. It is, however, significant only for high-energy electrons and positrons.



Figure 49: Dominant Feynman diagrams for a bremsstrahlung process $e^-+ (Z,A) \rightarrow e^-+ \gamma + (Z,A)$

- Solution to bremsstrahlung from nucleus field is of order $Z^2 \alpha^3$, and from atomic electrons of order $Z \alpha^3$ (α^3 from each electron).
- For relativistic electrons, average rate of bremsstrahlung energy loss is given by:

$$-\frac{dE}{dx} = \frac{E}{L_R}$$
(36)

The constant L_R is called the radiation length:

$$\frac{1}{L_R} = 4 \left(\frac{\hbar}{mc}\right)^2 Z(Z+1) \alpha^3 n_a \ln\left(\frac{183}{Z^{1/3}}\right)$$
(37)

In Equation (37), n_a is the density of atoms per cm^3 in medium.

Radiation length is the average thickness of material which reduces mean energy of a particle (electron or positron) by factor e.

Interactions of photons in matter

- Main contributing processes to the total cross-section of photon interaction with atom are:
 - Photoelectric effect ($\sigma_{p.e.}$)
 - Ompton scattering (σ_{incoh})
 - Pair production in nuclear and electron field (κ_N and κ_e)



Figure 50: Photoelectric effect (left) and Compton scattering (right)



Figure 51: Pair production

At high energies, pair production is the dominant process: $\sigma_{pair} = 7/9n_a L_R$, and number of photons travelled distance *x* in matter is

$$I(x) = I_0 e^{-7x/9L_R}$$



Figure 52: Photon interaction cross-section on a lead atom

 \bigcirc Note that pair production occurs when photon energies reach $E > 2m_e$ (E > 1 MeV).

Particle detectors

Particle detectors consist of many subsystems:

- 1) Tracking devices coordinate measurements
- 2) Calorimeters energy measurements
- 3) Time resolution counters
- 4) Particle identification devices
- 5) Spectrometers momentum measurements



Figure 53: Assembly of the ATLAS detector

- Main principle: ionization products are either visualized (as in photoemulsions) or collected on electrodes to produce an electronic signal, to be processed by a computer
- Basic requirements of high-energy physics experiments:
 - \bigcirc High spatial resolution (\propto 10-100 μ m)
 - Possibility to register particles synchronously with a high rate (good triggering)
- To fulfil the latter, electronic signal pick-up is necessary, therefore photoemulsions and bubble chambers were ultimately abandoned
- Modern tracking detectors fall in two major categories:
 - Saseous detectors ("gas chambers"), resolution ~100-500 μ m
 - Semiconductor detectors, resolution ~ 5μ m

Proportional and drift chambers



Figure 54: The number of electron-ion pairs collected when a charged particle traverses a gaseous detector of average size, as a function of applied voltage



Figure 55: Basic scheme of a wire chamber

- ✤ A simplest proportional chamber:
- A conducting chamber, filled with a gas mixture, serves as a cathode itself, while the wire inside serves as an anode
- The field accelerates the electrons produced in ionization \Rightarrow secondary electron-ion pairs \Rightarrow avalanche of electrons \Rightarrow pulse in the anode. Amplification is $\propto 10^5$ for voltage of 10^4 - 10^5 *V/cm*. Gas mixture is adjusted to limit the avalanche.
 - Several anode wires ⇒ coordinate measurement possibility (Multi-Wire Proportional Chamber, MWPC)



Figure 56: Common view of the 2-dimensional MWPC

Alternative to MWPC : drift chambers



Figure 57: Basic scheme of a drift chamber

- Ionization electrons produced along the particle passage arrive to the pick-up anode at different times t_1 , t_2 , t_3 , ...
- knowing (from other detectors) the time of particle's arrival t_0 and field in the chamber, one can calculate coordinates of the track l_1 , l_2 , l_3 , ...
 - Streamer detectors are wire chambers in which secondary ionization is not limited and develops into moving plasmas – streamers
 - If H.V. pulse in a chamber is long enough, a spark will occur: *spark chambers*

Semiconductor detectors

In semiconducting materials, ionizing particles produce electron-hole pair. Number of these pairs is proportional to energy loss by particles



Figure 58: Typical silicon detector is a p-n junction diode operated at reverse bias

- Superior resolution (few μm), small size, small power consumption, fast signals.
- Subject to radiation damages; can be circumvented by using radiation-hard manufacturing processes, approriate handling (e.g. cooling) and by using very thin detectors.

<u>Calorimeters</u>

- To measure energy (and position) of the particle, calorimeters use absorbing material to capture all the energy of the particle.
- Signals produced in calorimeters are proportional to the energy of the incoming particle.
- During the absorption process, particle interacts with the material of the calorimeter and produces a secondary *shower* of particles.
- Since electromagnetic and hadronic showers are somewhat different, there are two corresponding types of calorimeters

Electromagnetic calorimeters



Figure 59: Electromagnetic shower; depth in radiation lengths

- \diamond Used for electron/positron and γ energy measurements
 - Opminant energy loss for high-energy electrons (or positrons) is bremsstrahlung: $e^{-} \rightarrow e^{-} \gamma$
 - ⁽◎ Photons produced via bremsstrahlung produce e^+e^- pairs and are thus absorbed again: $\gamma \rightarrow e^+e^-$
 - ^(◎) An initial electron thus produces a cascade of photons and e^+e^- pairs, until its energy falls under the bremsstrahlung threshold of $E_C \approx 600 \text{ MeV/Z}$
- A calorimeter has to be large enough to absorb all the possible energy of the incoming particle.
- Main assumptions for electromagnetic showers:
 - (a) Each electron with $E > E_C$ travels one radiation length and radiates a photon with $E_{\gamma} = E/2$
 - (b) Each photon with $E_{\gamma} > E_C$ travels one radiation length and creates an e⁺e⁻ pair, which shares equally E_{γ}
 - (c) Electrons with $E \le E_C$ cease to radiate; for $E \ge E_C$ ionization losses are negligible

These considerations lead to the expression:

$$t_{max} = \frac{\ln(E_0/E_C)}{\ln 2}$$
(38)

where t_{max} is number of radiation lengths needed to stop the electron of energy E_0 .

Electromagnetic calorimeters can be, for example, lead-glass (crystal) blocks collecting the light emitted by showers, or a drift chamber interlayed with heavy absorber material (lead).

Hadron calorimeters

- Used for hadron energy measurement (π , K, protons, neutrons)
 - Hadronic showers are similar to the electromagnetic ones, but absorption length is larger than the radiation length of electromagnetic showers since hadrons interact in the material through nuclear interactions.
 - Output Also, some contributions to the total absorption may not lead to a signal in the detector (e.g., nuclear excitations or secondary neutrinos)
- Main characteristics of a hadron calorimeter are:
 - (a) It has to be thicker than electromagnetic one
 - (b) Layers of ²³⁸U can be introduced to compensate for energy losses (low-energy neutrons cause fission)
 - (c) energy resolution of hadron calorimeters is generally rather poor
- Hadron calorimeter is usually a set of MWPC's or streamer tubes, interlayed with thick iron absorber

Scintillation counters

- Scintillation counters are widely used to detect the passage of charged particles through an experimental setup and to measure particle's "*time-of-flight*" (TOF).
- Scintillators are materials (crystals or organic) in which ionizing particles produce visible light without losing much of its energy
 - On the light is guided down to photomultipliers and is being converted to a short electronic pulse.



Figure 60: Scheme of a scintillation detector and photomultiplier assembly

Particle identification

- Output: Particles are identified by mass and charge: knowing momentum of particle is not enough to find those out, complementary information is needed.
- Solution For low-energy particles (E < 1 GeV), TOF counters can provide this complementary data.
- Since it is a state dE/dx dependence on particle mass for energies below ≈ 2 GeV (1/β² region of Bethe-Bloch formula)
- The most reliable particle identification device: Cherenkov counters
 - In certain media, energetic charged particles move with velocities higher that the speed of light in these media
 - Second Secon

The angle θ_{C} depends on the refractive index of the medium *n* and on the particle's velocity *v*:

$$\cos\theta_{\rm C} = c \,/\, vn \tag{39}$$



Figure 61: Cherenkov effect in the DELPHI RICH detector

Measuring θ_C, the velocity of the particle can be easily derived, and the identification performed: *p* is measured by a tracking device, *v* by the Cherenkov counter ⇒ m=p/v.

Transition radiation measurements

- ln ultra-high energy region, particles velocities do not differ very much
- Whenever a charged particle traverses a border between two media with different dielectric properties, a *transition radiation* occurs
- Intensity of emitted radiation is sensitive to the particle's energy $E = \gamma mc^2$.
- **(a)** Transition radiation occurs only if $\gamma > 1000$, which means E/m > 1000.

Transition radiation measurements are particularly useful for separating electrons from other particles: for electrons, $\gamma = 1000$ for E = 0.5 GeV. For pions, $\gamma = 1000$ for E = 135 GeV $\Rightarrow e/\pi$ separation between 0.5 and 135 GeV.

<u>Spectrometers</u>

♦ Momenta of particles can be measured by curvatures of tracks in a magnetic field: $p=0.3B\rho$, where ρ is curvature, *B* is magnetic field.

Spectrometers are tracking detectors placed inside a magnet, providing momentum information



Figure 62: A e^+e^- annihilation event as seen by the DELPHI detector. In collider experiments, all the tracking setup is typically contained inside a solenoidal magnet.



Figure 63: The DELPHI detector at LEP (operated in 1989 - 2001) ~10 meters long, 3500 tons



Figure 64: DELPHI detector being disassembled



Figure 65: ATLAS detector at LHC, operates since 2008 44m long, 7000 tons



Figure 66: ATLAS Inner Detector: semiconductor trackers and the transition radiation tracker



Figure 67: ATLAS Pixel Detector close-up



Figure 68: ATLAS inner trackers as seen by a particle



Figure 69: ATLAS calorimeters. LAr (for "liquid Argon"): EM and hadronic (absorbers: lead, copper, tungsten). TileCAL - hadronic, steel/scintillator



Figure 70: ATLAS muon systems



Figure 71: ATLAS solenoid (left) and end-cap toroid (right)



Figure 72: ALICE detector at LHC - dedicated to Pb-Pb collision measurements



Figure 73: CMS detector at LHC



Figure 74: LHC-b detector at LHC, dedicated to B meson studies



Figure 75: PHENIX detector at RHIC, dedicated to heavy ion collision studes



Figure 76: IceCube neutrino detector at the South Pole (left) is an array of photomultiplier modules (right)



Figure 77: PAMELA detector in space, dedicated to antimatter and astrophysics studies